

# **VISUM Release Notes**

**Version 11.5**

**Version 11.50-05**  
**Last modified: 2010-09-02**



Stumpfstr. 1  
D-76131 Karlsruhe  
Phone: +49 721 9651-313  
Fax +49 721 9651-299  
Hotline: [www.ptv-vision.com/hotline\\_visum](http://www.ptv-vision.com/hotline_visum)

### COM Interface

- ▶ *INode / IMainNode*: The COM method UpdateImpedance optionally writes a report, depending on procedure parameters. (9244)

### Data Model

- ▶ *Remove transport systems*: When removing a transport system blocks using it as empty trip transport system are removed as well. (9278)
- ▶ *System routes*: If a system route uses a turn, this turn must not be blocked for the transport system of this system route. (9235)
- ▶ *Fares*: The number of traversed fare zones is calculated correctly in complicated networks, too. (9242)
- ▶ *Signal controllers*: There are no rounding errors anymore when signalgroup-based controllers are converted to stage-based controllers. Since this conversion is used implicitly in signal cycle and split optimization, this may lead to minor differences in the results. (9243)

### Dialogs

- ▶ *Graphic parameters for diagrams*: Column diagrams are drawn correctly if there is more than one column, one of the attribute values is 0, and the option "hide if (absolute) value <=" is disabled. (2637)
- ▶ *Print settings*: The menu item "Set print page..." now works even in case a list view is active. Moreover, the menu item appears in the "Layout" menu as well now. (9175)
- ▶ *Attribute selection*: The program will no longer crash if one tries to add an alias pointing to an attribute with sub-attribute that does not exist any more in the attribute selection dialog. (9270)
- ▶ *PuT fares*: Multiple minor grid bugs were fixed. (9241)

### Timetable Editor

- ▶ *Block display*: The program will no longer crash if a block is inserted while the tree showing all blocks is open and if the insertion is canceled within the dialog. (9271)
- ▶ *Block display*: When creating a user-defined block item, the blocking day will always be determined correctly from the insert position. (9272)

### Foreign Formats

- ▶ *SVG export for Inkscape*: Point symbols are scaled correctly. (8845)
- ▶ *Import shapefile*: Point objects do not lose their coordinates when importing as stops. (9229)

### Graphics

- ▶ *Desire lines*: Desire line links are drawn if the bar layer is switched off. (8751)
- ▶ *Turn volume parameters*: When editing graphic parameters of text blocks in Turns->Turn volumes->Text format->Standard, the new settings can optionally be applied to all active turn volumes. (9173)
- ▶ *Draw link bars*: Link bar labels are no longer moved by the link's width if the bar layer is switched off. (9252)
- ▶ *SVG as background in VISUM*: Dashed lines are displayed correctly. (6944)
- ▶ The network no longer disappears when pasting empty list contents. (9261)
- ▶ *Version comparison*: Bars of percental difference attributes are displayed correctly now. (9283)
- ▶ Background JPEG images larger than 500x500 pixels were always exported in black and white when printing to a PDF. (9257)
- ▶ *Turn volumes*: Bars on straight turns are displayed correctly now. (9233)

### Graphical Operations

- ▶ *Read network file additively and shortest path search*: If a PrT shortest path search has been executed in a network, when reading a network file additively the shortest path search will no longer be executed after each line containing a turn, but only once when reading the file is finished. This speeds up reading network files in this case. (4147)

### Listings

- ▶ *PuT partial routes*: Indirect attributes of ticket types are updated correctly on network changes now. (9246)

## Matrix Editor

- ▶ *Matrix histogram*: VISUM no longer crashes if all intervals are deleted in a histogram of multiple matrices. (9259)
- ▶ *Matrix histogram*: All toolbar icons of the matrix editor now work correctly if both matrix editor and matrix histogram are open. (9258)
- ▶ *Layout*: The matrix editor supports saving and loading layout files from now on. (5031)
- ▶ *Graphic parameters*: Graphic parameters for the matrix editor are available now. They can be used to produce a classified depiction of grid cells and can be stored in a parameters file. (5168)
- ▶ *Histogram*: The program will no longer crash when opening a version file or creating a new network while a matrix histogram is open. (9265)

## Miscellaneous

- ▶ *Context sensitive online help (fare systems)*: The context sensitive online help now works for all the pages of the fare system dialog. (9279)
- ▶ *Copy & paste in matrix editor*: Copy & paste from matrix editor into excel maintains newlines on chinese operating systems as well. (9177)

## PuT Line Blocking

- ▶ *Block check*: The program will no longer freeze (endless loop) while executing the block check procedure if, by inserting empty trip items, the standard sort order of block items is changed. (9119)
- ▶ *Block Check*: Layover times before the first and behind the last service trip block item are maintained when checking open blocks. (9216)
- ▶ *Blocks*: The program will no longer crash if changes to the pre or post preparation times leads to the deletion of the corresponding block item. (9250)

## PrT Assignment

- ▶ *Equilibrium-Lohse and stochastic assignment*: The range of the termination parameter has been enlarged s.t. a factor of 0 can be used instead of 0.01. (9253)

## PuT Assignment

- ▶ *Connection import*: VISUM no longer crashes if reading network volumes fails. (9239)

## VISUM Files

- ▶ *Attribute files*: The program will no longer crash when reading an attribute file containing a column named as an alias existing in the current network and pointing to an attribute with sub-attribute. (9269)

11.50-04

Corrections, Bug Fixes and New Features (ID)

2010-08-23

## Add-In

- ▶ *Add-Ins*: The window header now always matches the title of the document. (9148)

## COM Interface

- ▶ *Shorten a line route*: This functionality will no longer freeze. (9204)

## Dialogs

- ▶ *Set up and edit classification*: Setting up the class limits now works correctly. (9225)
- ▶ *Save network*: The table and attribute selection is no longer reset if one of the options is checked: "Save only active network objects", "Hide empty tables", "Hide attributes with default values". (8822)
- ▶ *Edit line route*: Arrival and departure times are editable now. (7718)
- ▶ *Line route dialog*: The arrival and departure data is correct now, even if an additional stop event with dwell time > 0 was added above a reference point. (9211)

## Timetable Editor

- ▶ *Block display*: The valid days label uses "not valid" for days outside calendar now, when searching for a matching valid days object in the network (9195)

## Filters

- ▶ *Filter dialog*: In certain cases, VISUM used to crash if the first data row in the filter conditions grid was deleted. This bug could be fixed. (9223)

## Graphics

- ▶ *Set up and edit classification*: Automatic class limits can now also be calculated with natural breaks. (8868)

## Matrix Editor

- ▶ *Arithmetic operations*: The buttons for rounding and linear combination of matrices and vectors now work correctly. (9218)
- ▶ *Old matrix editor*: (1) Upon closing a matrix the reference in the list of open matrices is removed. (2) Code files are now displayed correctly. (9187)

## Demand Operations

- ▶ *Demand procedures*: The procedures can now be applied independently of existing add-ons. (9220)

## Network Editor

- ▶ *Version comparisons*: A suffix is now added to user defined attributes (same as for other attributes). (9208)

## PrT Assignment

- ▶ *LUCE using an existing assignment as initial solution*: The procedure will no longer produce instable results which used to occur in certain cases. (9171)

## VISUM Files

- ▶ *Open / Save procedure parameters*: An entry is written in Trace.txt when a parameter file (.xml or .par) is opened / saved successfully. (9228)
- ▶ *Project directories files*: pfd files can now also be read when they contain additional whitespace. (9217)

11.50-03

Corrections, Bug Fixes and New Features (ID)

2010-08-16

## COM Interface

- ▶ *SetMultiAttValues*: This method checks the validity of the index ( $[x,0]$  in the first place of the array). (9201)
- ▶ *Log files*: The COM methods WriteToTrace and WriteToError add a line break to complete the generated entry. (9164)

## Data Model

- ▶ *Matrix cache*: In certain cases, defragmentation of the matrix swap file caused a program crash. This bug could be fixed. (9181)
- ▶ *Edit line route shape*: The program no longer crashes when the line route is lengthened. (782)
- ▶ *Line blocks*: The program will no longer freeze (endless loop), if the pre and post preparation times of vehicle journey sections are reduced, though a shorter time had been set manually for the the layover block items in the line blocks before. (9186)

## Dialogs

- ▶ *Column Charts*: Attributes with an ID consisting of one character only may be used as label for x-axis (used e.g. for russian short name of link attribute 'NO'). (9169)
- ▶ The program will no longer freeze (endless loop) if a warning or an error message appears in the process window of a separate thread while the procedure is running. (9182)
- ▶ *Shapefile export*: Unlike the regular mode, the OK button is initially selected in the attribute selection dialog and the Cancel button aborts the operation. (8662)

## Difference Network

- ▶ *Network merge mode*: Merging the networks works now while a list of user-defined paths is open. (9190)

## PuT Passenger Survey

- ▶ Read passenger onboard data from file (either data format): The program will no longer crash, if the target network is empty. (777)

## Timetable Editor

- ▶ The Screenshot functionality now works in the timetable editor, too. (9194)
- ▶ *Set PuT line selection via COM*: Setting the line selection for the timetable editor via COM does not produce invalid sequences of stops or stop points. (9183)

## Filters

- ▶ *Group filter*: The filter state is now updated when an object is created. (779)

## Graphical Operations

- ▶ *Flow bundle*: The flow bundle is recalculated again after changes to the OD pair filter. (9199)

## Listings

- ▶ *Goodness of PrT assignment with ICA list*: In certain cases, the program used to crash when assignment results were discarded while the list was open. This bug could be fixed. (9168)

## Matrix Editor

- ▶ Via the filter icon in the matrix editor toolbar, filtering can globally be switched on or off. (9178)
- ▶ *Multi-matrix processing*: Operations on matrices, which themselves are the second operand for other matrices, are performed at last. In this way, the operation regards the original value of the operand. (8584)
- ▶ *Matrix histogram*: Interval files in old format (extension .cod) can now be read. (9166)

## Network Editor

- ▶ *Edit zone shape*: The program will no longer freeze (endless loop), if the user clicks a polygon point that belongs to two adjacent polygons while holding down the CTRL and SHIFT keys. (9144)
- ▶ When aggregating lines, all line routes that can be aggregated are now actually aggregated in one procedure run – independent of the order of the IDs. (7487)
- ▶ Like in web browsers, the keyboard can be used now to navigate in the view history, i.e. the key combinations Alt - Arrow left and Alt - Arrow right can be applied. (8451)

## PuT Operating Indicators

- ▶ Saving version data to file works correctly even if the network includes PuT operating indicators for Territory x [...] x Vehicle combination, though some entries do not have a vehicle combination. (9191)

## Other Operations

- ▶ All procedures will warn interactively if an error occurs. Warnings will also be logged in trace- and error-files. (9153)
- ▶ The procedure Linear combination of matrices and vectors has been implemented in the matrix editor and also in the matrix browser, UNDO can be applied in either case. Target matrices can be among the source matrices. (9170)

## Miscellaneous

- ▶ *Open version via double-click*: When a version file is opened by double-click in the explorer, the file name spelling (upper and lower case) is retained. (9176)
- ▶ Reduced memory fragmentation after assignment calculations. (8050)

## PrT Assignment

- ▶ *PrT assignment with ICA*: The assignment is now considered to have reached convergence only if the internal assignment (Equilibrium\_Lohse or Equilibrium assignment) has reached convergence, too, and was not terminated because the maximum number of iterations had been reached. (9172)
- ▶ Deleting PrT assignment results for multiple demand segments has been accelerated. (9188)
- ▶ *LUCE with warm start*: The procedure returns sufficient volumes now even if traversed network objects were blocked in the initial solution. Results are not fully stable numerically, but this issue will be addressed shortly. (9197)

## PuT Assignment

- ▶ *Connection import*: Even if an error occurred, the process window is closed (for example, if the file to be imported does not exist). (9167)
- ▶ *Connection import*: VISUM now rejects path legs using time profiles backwards. (9206)

11.50-02

Corrections, Bug Fixes and New Features (ID)

2010-08-04

## Add-In

- ▶ *Balance matrix*: The user is now notified if the matrix contains invalid values. (9087)
- ▶ *Add-In 'EVA Auswertung'*: No crash if EVA-Demandmodel is incomplete (9135)

## COM Interface

- ▶ Interactive deletion of current network is prohibited if COM references to network objects exist. (9081)

## Data Model

- ▶ The growth of the matrix swap file is decreased much. (8839)
- ▶ *Emission calculation according to HBEFA*: If a fleet composition has no subsegment with a positive weight, this results in a uniform distribution of all segments of the selected categories in the calculation and in the linear combination of fleet compositions. (8988)
- ▶ *Lines*: The transport system of a line can be changed at any time. Where required, network objects to be opened (links, turns, stop points) will be adjusted. (6771)

## Dialogs

- ▶ Dialog "Comparison of stop and run times" does not crash any more if only active objects are displayed and filtered by system routes (9157)
- ▶ *File names*: When using the 'Open' or 'Save as' command, the default extension of the respective file type is added to file names which do not have a valid extension yet. If, in the project directories, a '\*' has been entered for the file type, any extension is permitted. In this case, no additional extension is added. (6082)
- ▶ *Forced chainings dialogs*: In the Forced chainings dialog and in the wizard to define new forced chainings, the column selection for the table can now be set. The columns with calculated departure, arrival and valid days are always displayed. (9075)
- ▶ *Edit stop dialog*: The specific walk and wait times between time profiles are displayed correctly. (9131)
- ▶ *Tooltips*: Tooltips with umlauts are translated correctly on operating systems with a 'foreign' codepage. (9099)
- ▶ *Blocking back model*: The input field for the average space required per car unit now also handles imperial units correctly and full stop or comma as decimal separators. (9107)

## Timetable Editor

- ▶ *Line block view*: The printout is positioned better than before. (9092)
- ▶ Context menu entries in the timetable editor which refer to marked vehicle journeys are grayed out, if nothing has been marked. Context menu entries that require further user input are identified by "...", as usual. (9121)
- ▶ *Parameter dialog for line block display*: The combobox of block versions for the determination of unbound actions is sorted numerically by the block version number. Furthermore, the previous block version selection can be restored more often than before when reopening the dialog. (9078)
- ▶ *Wizard to define forced chainings*: A progress dialog is displayed when determining the possible targets. The determination can be cancelled. In this case, any already determined targets will be displayed. (9076)

## Filters

- ▶ *Filter on vehicle journey items*: vehicle journey items are passive, if their vehicle journey is passive. This could be wrong if the journey was passive, because of a filter on vehicle journey sections (8697)

## Foreign Formats

- ▶ *Shapefiles*: Z- coordinates of nodes are now exported/imported correctly. (9097)
- ▶ PolygonM+Z behave just like Polygon. The z-coordinates/the measured value cannot be used in

EdgePoint and are thus discarded. (4362)

## Graphics

- ▶ *Legend*: When scaling path bars, the legend now also displays the specified attribute. (9120)
- ▶ The initial graphic parameters classification is calculated from existing classes (9126)
- ▶ Text labels of print frames can have multiple lines and are wrapped automatically (7179)
- ▶ *Editing classifications*: If you edit an existing classification, the current color gradients are transferred to the dialog as far as possible. (8870)
- ▶ *Lists*: *The correct font size is set when printing (so far: the font size of the header).* (9091)
- ▶ *Line bars*: the aggregate function "weighted mean" also regards the first attribute value now (9141)

## Junction Editor

- ▶ If you set the display language to Russian, the labels of the radio buttons ('legs', 'lanes') and check boxes ('Major flow manually') are now displayed in full. (9110)

## Matrix Editor

- ▶ *Integrated matrix editor*: Row and column sums are now available. (9158)
- ▶ Standalone matrix editor ("Muuli"): Changing options and saving of changed matrices works again. Also creating and editing a code file works again. (9163)
- ▶ *External matrices*: The initialization of external matrices no longer leads to a crash. (9105)

## Demand Operations

- ▶ *EVA mode choice*: If balancing is not possible in the network yet demanded in the procedure parameters, this is changed when opening the parameters dialog. A message is issued concerning the modification in the procedure parameters. (9045)
- ▶ *Estimating gravitation parameters*: You can now also add an interval via COM. Furthermore, a characteristic of the enum ProtocolSaveTypeT has been changed once more. (9103)
- ▶ *VISEM combined*: The transformation of the utility matrix is calculated after LogSums now (was calculated too early) (9137)
- ▶ *Procedure parameters for demand distribution dialog*: On the 'Function graph' tab, the parameters estimated with the Kalibri procedure are displayed, if the respective 'Apply estimated parameters' option has been set. (9100)
- ▶ *Estimating gravitation parameters and TFlowFuzzy*: It is possible to read interval-Att-files for the procedures (9101)

## Network Editor

- ▶ *Demand segments*: VISUM no longer crashes when discarding line costing results, for example due to the creation or deletion of a new demand segment. (9124)
- ▶ *Transport system*: When inserting a transport system, another transport system can be specified. From this transport system, the trafficability of the network and other transport system-dependent attributes are copied. (9047)

## Other Operations

- ▶ All procedures will warn interactively if an error occurs. Warnings will also be logged in trace- and error-files. (9153)

## Miscellaneous

- ▶ VISUM now starts even if UAC is activated, user has no admin permission and a scriptmenu entry for 'Computer' exists. (9116)
- ▶ VISUM respects HIGH DPI (120 DPI, 144DPI) (8187)
- ▶ Procedure "Save Version" occasionally generated a confusing warning if the filepath wasn't valid. (9132)

## PuT Line Blocking

- ▶ *Line blocking with vehicle interchange*: The procedure can generate blocks with predetermined secondary properties (long/short blocks, distribution of the layover times), just like the procedure without a vehicle interchange. (7752)
- ▶ *Line blocking with vehicle interchange*: The procedure converges further than before, so that better solutions are found. In addition, the procedure has been accelerated. (9112)

### PrT Assignment

- ▶ The Tribut learning procedure has been accelerated considerably. (9114)
- ▶ *LUCE assignment procedure*: The procedure can now build on an existing result from previous runs. (8941)

### PuT Assignment

- ▶ *Connection files*: The export and import of connection files has been parallelized. (7352)
- ▶ *Headway-based assignment*: In case of lines operating in parallel, only the last stop of multiple equivalent stops is used for transfers. (9129)

### VISUM Files

- ▶ Conflict avoidance works correctly if signal groups are read additionally from a network file (8075)
- ▶ *Network writing*: If "only active" is selected, only couple sections are written which have active couple section items (9090)
- ▶ *Additive network reading*: The 'Cancel' option as conflict handling for line route or time profile items led to a termination of the additive network reading. So far, the effected items were overwritten in this case. (765)
- ▶ *Model transfer file*: The model transfer file now contains less central types from the network file and the demand file. (8847)
- ▶ *Saving a network*: In the "Save only active network objects" mode, the program only exports time profile transfer times that belong to active time profiles. (9142)

### TFlowFuzzy

- ▶ Correct shares of the given matrix are now calculated, when selecting the 'Shares due to the matrix' option. (9143)